



Instructions for use: JURA Coffee Professional

Android

en

# Table of contents

<b>1</b>	<b>What is JURA Coffee Professional?</b>	<b>4</b>
<b>2</b>	<b>First steps</b>	<b>5</b>
<b>3</b>	<b>Smart Connect from JURA</b>	<b>6</b>
3.0.1	Inserting Smart Connect	6
3.0.2	Connecting to the machine	6
<b>4</b>	<b>Basic functions</b>	<b>7</b>
4.1	Home page	7
4.2	Connect	8
4.2.1	Connect app to machine	9
4.2.2	Connected to machine	10
<b>5</b>	<b>Preparation</b>	<b>11</b>
5.1	Countdown	12
5.2	Overview during preparation	13
<b>6</b>	<b>Menu</b>	<b>14</b>
	Settings	14
<b>7</b>	<b>Product settings</b>	<b>15</b>
7.1	Product configuration	17
7.2	Adjusting the product settings	18
7.3	Selecting a product	19
7.4	Create and edit folders	20
<b>8</b>	<b>Statistics</b>	<b>22</b>
8.1	Statistics – Current	22
8.2	Product counter	24
	Pie chart	26
8.3	Day counter	27
8.4	Maintenance counter	28
8.5	Messages	29
8.6	Machine settings	30
8.6.1	PIN function	30
	Activating the PIN function	31
	Deactivating the PIN function	31
	Changing the PIN	32
8.6.2	Smart Connect software update	33
8.7	Version	34
8.8	Statistics – Archive	35
<b>9</b>	<b>General settings</b>	<b>37</b>
9.1	Block access to menu	38

- 9.2 Switch off machine display ..... 38
- 9.3 Permit one-off settings while your drink is being prepared. .... 38
- 9.4 Defining the current position ..... 39
- 9.5 Countdown ..... 39
- 9.6 Software version ..... 40
- 9.7 Statistics settings ..... 41
  - 9.7.1 Enter e-mail sender..... 42
  - 9.7.2 Automatic notifications for readings..... 43
    - Activate or deactivate automatic notification..... 44
    - Specify e-mail address ..... 45
    - E-mail frequency ..... 45
    - E-mail format ..... 45
    - CC sender..... 45
    - Automatically reset day counter ..... 45
  - 9.7.3 Automatic notifications for messages..... 46
    - Automatic notifications for group 1 messages ..... 47
    - Enable automatic notifications..... 47
  - 9.7.4 Configuration wizard ..... 48
    - Welcome to the configuration wizard ..... 48
    - Inserting Smart Connect ..... 49
    - Connecting to the machine ..... 50
    - E-mail configuration ..... 51
    - E-mail configuration test ..... 52
    - Send readings ..... 53
    - Test readings ..... 54
    - Send messages ..... 55
      - Group 1 messages ..... 55
      - Group 2 messages ..... 55
      - Message configuration test..... 56
    - Ending wizard ..... 57
- 9.8 Clear application cache..... 58
- 10 Help / instructions..... 59**
- 11 Notifications..... 60**
  - 11.1 E-mail containing machine readings:..... 61
  - 11.2 E-mail containing machine message ..... 62
- 12 Support for different languages..... 63**

# 1 What is JURA Coffee Professional?

The JURA Coffee Professional App conveniently brings the various setting and programming options of your automatic machine\* to your tablet. Customise your favourite specialities, give them creative names or assign any image you want to them. The preparation can of course also be started from the tablet.

All you need is the optional Bluetooth® transmitter Smart Connect from JURA and this app.

\*The following automatic coffee machines are compatible with the JURA Coffee Professional App:

- GIGA X9/X9c Professional
- GIGA X8/X8c Professional
- GIGA X7/X7c Professional
- GIGA X3/X3c Professional
- GIGA W3 Professional

You can find the latest list of compatible coffee machines at [www.jura.com/smartconnect](http://www.jura.com/smartconnect)



Under certain circumstances, the app may not contain the latest list of machines. If this is the case, connect to the Internet before launching the app.

## 2 First steps

To make full use of the JURA Coffee Professional App you will need

- **Smart Connect** from JURA, inserted into a compatible machine.
- a tablet with
  - **Android version 4.4** (or higher).
  - **Bluetooth version 4.0** (or higher).



If the app doesn't work despite the above requirements being met, this may be due to the particular system settings of the tablet manufacturer.

## 3 Smart Connect from JURA

### 3.0.1 Inserting Smart Connect

The Smart Connect must be inserted into the coffee machine's service socket. This is usually on the top or back of the machine, beneath a removable cover. If you don't know where the service socket of your coffee machine is, ask your dealer or visit [www.jura.com](http://www.jura.com).

### 3.0.2 Connecting to the machine

Once the Smart Connect is inserted, it automatically searches for all machines within range (approx. 3 m).

Tap on the machine you want to connect to.

#### **PIN function (optional):**

The PIN function on the Smart Connect is deactivated by default.

If the PIN function has been activated, at this point you will be prompted to enter the PIN.

If the correct PIN was entered when the connection to the machine was established, this is stored in the app and does not have to be entered again to re-connect. If the PIN is changed later on, it must be entered again in order to connect.

The PIN function can be changed in the machine settings.

# 4 Basic functions

## 4.1 Home page

The user interface of the JURA Coffee Professional App can be split into two areas:

- **Top bar** (beside the app logo)
  - Drop-down menu
  - Name of the current screen
  - Symbol for connection status
- **Product list:** Adjustable area where the products available on the connected machine are shown.




Fig. 1: Home page

## 4.2 Connect

In order to use the app functions you must connect to a machine within range. If you are on the start screen, tap on the red machine symbol in the top right.




Fig. 2: Connection screen



## 4.2.1 Connect app to machine

To show the machines available within range, tap on "SCAN".

The range of the Bluetooth connection is approx. 3 m. Available machines are now shown on this screen. Select the machine to which the app is to connect.

Please note that under some circumstances the app cannot connect to all the machines listed. The app cannot connect to any "unknown" or "unsupported" machines.




Fig. 3: Machine found within range

## 4.2.2 Connected to machine

Once you have selected an available machine, after a short wait the connection is established.




Fig. 4: Connected to machine

# 5 Preparation

Tap the icon of the desired product to start preparation.

The available products may vary depending on the connected machine. If more than 12 products are available they are shown on additional pages.

If an accounting system is connected to the automatic coffee machine, preparations cannot be started by the app.



Fig. 5: Products which can be prepared using the connected machine

# 5.1 Countdown

After a product is selected, the countdown to the start of preparation is displayed. You can disable the countdown or adjust the times in the general settings.

If you don't want to prepare the selected product, tap on "Cancel preparation".




Fig. 6: Countdown

## 5.2 Overview during preparation

In this screen you can track the progress of preparation, change the quantities or cancel preparation:

- Tap on "-" or "+" to change a quantity (e.g. amount of milk foam).
- Tap on "Cancel preparation" to stop preparation. If the product has more than one ingredient, e.g. milk foam and coffee, the machine only stops preparing the current ingredient.




Fig. 7: Preparation – Latte macchiato

# 6 Menu

This menu gives you access to all areas and functions of the app.




Fig. 8: Menu

## Settings

In the “Settings” area you can:

- call up the general settings (see chapter 9)
- go straight to the machine settings for the machine **currently connected** (see chapter 8.6)




Fig. 9: Settings

# 7 Product settings

In the "Product settings" area you can configure all available products on the currently connected or last connected machine. In this screen you can also:

- Add more products to the start screen – tap on "+" (top right).
- Remove displayed products – tap and keep your finger on the product icon and then drag it to the trash can icon.
- Reposition a product – tap and keep your finger on the product icon and move it to another position.
- Store (group) products in a folder – to do this, tap and hold the symbol for a product and slide it up to the folder symbol. Then you can change the name and photo for the folder and store more (max. 8) products in it.




Fig. 10: Product settings




Fig. 11: Remove product from start screen



Fig. 12: Change position on start screen



# 7.1 Product configuration

When you tap on a product in "Product settings", the product configuration page opens. Here you can change the individual parameters for the product.




Fig. 13: Product configuration – Latte macchiato

## 7.2 Adjusting the product settings

To change the individual parameters of the selected product, tap on the value you want to change. Then confirm by pressing "Save".





Fig. 14: Adjusting the product settings – Coffee strength

## 7.3 Selecting a product

In this product selector you can select the products to be displayed on the start screen. You can also select the same product more than once in order to change and personalise the various parameters later on.

The selected product is added to the start screen. If there are already more than 12 products on this screen the product is added on a new page.



**Fig. 15:** Selecting a product

# 7.4 Create and edit folders

Tap and hold the symbol for a product and slide it up to the folder symbol. Then you can change the name and image of the new folder and add more (max. 8) products.



Fig. 16: Create folder




Fig. 17: Newly created folder on home page




Fig. 18: Folder view on home page




Fig. 19: Folder view on "Product settings" page

## 8 Statistics

Choose between "Current" and "Archive".



Fig. 20: Statistics

### 8.1 Statistics – Current

This screen can be split into three areas:

- **Top bar:**
  - Back button
  - Name of connected machine
  - Symbol for connection status
- **Data bar:** Drop-down menu and horizontal scrollbar with the following functions:
  - Drop-down menu – Here you can call up various actions for the first four options from the data bar (product counter, day counter, maintenance counter and messages), e.g. show a pie chart, reset the day counter or send e-mails containing messages
  - Product counter
  - Day counter
  - Maintenance counter
  - Messages
  - Machine settings
  - Version

- **Content section:** Area displaying information about the option selected from the data bar above

To go **back to the machine selection list**, tap on the small arrow on the left in the top bar.

The screenshot shows the JURA Coffee Professional app interface for a GIGA X3 Professional machine. The top navigation bar includes a back arrow, a hamburger menu, and icons for Product counter, Day counter, Maintenance counter, Messages, Machine settings, and Version. The main content area displays 'Last update: Never' and a table of product counts.


Total number of products		0
Ristretto	0 Espresso, large (Americano)	0
Espresso	0 Coffee, large	0
Coffee	0 Cappuccino, large	0
Fiat White	0 Latte macchiato, large	0
Cappuccino	0 Café au lait, large	0
Latte macchiato	0 Portion of milk, large	0
Café latte	0 Hot water, large	0
Macchiato	0 Jug 2	0
Hot water	0 Milk (continuous)	0
1 portion milk	0 Milk foam (continuous)	0
1 portion milk foam	0 Hot water (continuous)	0
Jug of coffee	0 Marocchino	0

**Fig. 21:** Machine connected for the first time

## 8.2 Product counter

Below the product counter button you can see the date on which data was last read from the connected machine. The various readings for the connected machine are displayed below this.

If this is the first time that you have connected to a machine with the app, you are asked to read the data.



The screenshot shows the 'Product counter' screen in the JURA Coffee Professional app. The machine model is 'GIGA X3 Professional'. The status 'Last update: Never' is displayed at the top. Below is a table with 14 rows, each representing a different coffee product and its count, which is zero for all items.

Total number of products		0
Ristretto	0 Espresso, large (Americano)	0
Espresso	0 Coffee, large	0
Coffee	0 Cappuccino, large	0
Flat White	0 Latte macchiato, large	0
Cappuccino	0 Café au lait, large	0
Latte macchiato	0 Portion of milk, large	0
Café latte	0 Hot water, large	0
Macchiato	0 Jug 2	0
Hot water	0 Milk (continuous)	0
1 portion milk	0 Milk foam (continuous)	0
1 portion milk foam	0 Hot water (continuous)	0
Jug of coffee	0 Marocchino	0

Fig. 22: Product counter



JURA Coffee Professional		GIGA X3 Professional	
<span>Product counter</span> <span>Day counter</span> <span>Maintenance counter</span> <span>Messages</span> <span>Machine settings</span> <span>Version</span>			
Last update: Never			
number of products		0	
Espresso	0 Espresso, large (Americano)	0	
Espresso	0 Coffee, large	0	
Coffee	0 Cappuccino, large	0	
Flat White	0 Latte macchiato, large	0	
Cappuccino	0 Café au lait, large	0	
Latte macchiato	0 Portion of milk, large	0	
Café latte	0 Hot water, large	0	
Macchiato	0 Jug 2	0	
Hot water	0 Milk (continuous)	0	
1 portion milk	0 Milk foam (continuous)	0	
1 portion milk foam	0 Hot water (continuous)	0	
Jug of coffee	0 Marocchino	0	

Fig. 23: Selection of actions for product counter

# Pie chart

The pie chart is in the drop-down menu for the data bar. It is divided into the following groups:

- Speciality coffees
- Products with ground coffee
- Specialities with milk
- Hot water

To see which products belong to each group, tap on an area inside the pie chart or one of the associated buttons.




Fig. 24: Product counter pie chart

### 8.3 Day counter

Below the day counter button you can also see the date on which data was last read from the connected machine. Please note that the day counter always provides readings for a certain period and not the total number of products ever prepared. You will find these readings under "Product counter".

In the data bar drop-down menu you can **reset the day counter**.




Fig. 25: Day counter

## 8.4 Maintenance counter

The number of maintenance programmes carried out (cleaning, descaling, etc.) can be seen under the maintenance counter button. You can also see the current maintenance status, i.e. when the machine next needs maintenance.

Last update: 2016-01-14 15:08:25	
Cleaning operations	5
Filter change	8
Descaling operations	4
Milk system rinsing operations	889
Coffee system rinsing operations	566
Milk system cleaning operations	3
Cleaning	<div style="width: 0%;"></div> 0%
Filter change	No filter
Descaling	<div style="width: 3%;"></div> 3%

Fig. 26: Maintenance counter

## 8.5 Messages

Under "Messages" you will find a list of the display messages currently displayed on the connected machine, e.g. "No drip tray" or "Fill the bean container" and information as to whether the machine is in programming mode.




Fig. 27: Messages

## 8.6 Machine settings

You can individually adapt the name and location of the connected machine. The adapted information is automatically updated throughout the app.




Fig. 28: Machine settings

### 8.6.1 PIN function

You have the option of assigning a PIN to the Smart Connect installed in the coffee machine, for example to prevent unwanted readout of data. The PIN function on the Smart Connect is deactivated by default.

If the correct PIN was entered when the connection to the machine was established, this is stored in the app and does not have to be entered again to re-connect. If the PIN is changed later on, it must be entered again in order to connect.

## Activating the PIN function

Turn the controller to the "ON" position. Then follow the steps as prompted:

- Enter new PIN
- Confirm new PIN




Fig. 29: PIN function activated

## Deactivating the PIN function

To deactivate the PIN function you must enter the current PIN for the Smart Connect.

## Changing the PIN

You can change the PIN. To do this, touch "Change PIN" and follow the steps as prompted:

- Enter old PIN
- Enter new PIN
- Confirm new PIN




Fig. 30: Confirm new PIN



## 8.6.2 Smart Connect software update

The firmware version of the Smart Connect can be updated if a newer version is available. This requires an Internet connection.

Tap on "Smart Connect software update". If a new version is available, you can now update the app.

To finish the update process the connected machine is switched off. You are requested to switch the machine on again to complete the update.





Fig. 31: Firmware update

## 8.7 Version

The "Version" area contains various information about the connected machine and app.



JURA Coffee Professional		GIGA X3 Professional	
Product counter	Day counter	Maintenance counter	Messages
Machine settings		Version	
Main software version	EF722M T05.31		
Article number	15002		
Machine number	5270		
Serial number	2		
Production date	2014-07-11		
JURA Coffee Professional version	1.0.0		
Smart Connect version	V05.00F		
PIN for Smart Connect	PIN function deactivated		

Fig. 32: Version

## 8.8 Statistics – Archive

You can access data records from previous connections in the connection history. As well as the machine name and location, the date and time of the connection are also shown.

The data records listed in the connection history are always saved as soon as you read the counters and/or messages on a connected machine.




Fig. 33: Archive

The data records within the connection history correspond to those that you can read during a live connection, e.g. pie charts of day counters or messages. This information can also be sent by e-mail.

The screenshot shows the 'JURA Coffee Professional' app interface for a 'GIGA X3 Professional' machine. The top navigation bar includes options for 'Product counter', 'Day counter', 'Maintenance counter', 'Messages', 'Machine settings', and 'Version'. The data is as of '2016-01-14 12:50:58'. The table below lists various coffee products and their counts.

Total number of products		4899
Hot water	2317 2 espressi	11
Cappuccino	461 2 portions milk	9
Latte macchiato	315 Café au lait, large	9
Ristretto	286 Espresso, large (Americano)	8
1 portion milk	265 Summer Fire	8
Coffee	225 Shakerato	7
Flat White	170 Ground coffee	6
Espresso	111 2 cappuccini	6
1 portion milk foam	89 2 latte macchiati	6
Hot water (continuous)	82 Gourmet Latte Macchiato	6
Jug of coffee	74 2 caffè latte	4
Café latte	66 Latte macchiato, large	4

Fig. 34: Data record (extract) from a previous connection

# 9 General settings

In the general settings, you can configure the basic functions of the app:

- Block access to menu
- Switch off machine display
- Permit one-off settings while your drink is being prepared.
- Undertake various e-mail settings.
- Allow the configuration wizard to guide you through various settings
- Clear the app cache (this deletes all settings and data)




Fig. 35: General settings

## 9.1 Block access to menu

Enter a PIN to prevent access to app functions and settings. If an incorrect PIN is entered three times in a row, access to the app is blocked for one hour. During this time you cannot re-enter the PIN.

If you forget the PIN, you can have it sent to an e-mail address you have previously saved. You can enter this e-mail address in the statistics settings (see chapter 9.7.2).




Fig. 36: Access to menu blocked

## 9.2 Switch off machine display

The machine display is switched off as soon as the machine is connected to the tablet. This disables the machine's buttons.

## 9.3 Permit one-off settings while your drink is being prepared.

Enable or disable the function that allows product settings to be made during preparation.

## 9.4 Defining the current position

You can allow the app to access your current position.

## 9.5 Countdown

Define the countdown after which the product is prepared.




Fig. 37: Countdown

## 9.6 Software version

Here you can find out the app version and the file version of the supported machine at any time.




Fig. 38: Software version



# 9.7 Statistics settings




Fig. 39: Statistics settings

## 9.7.1 Enter e-mail sender

In order to correctly use the app you will need a Google e-mail account.

### Different e-mail recipients

Within the app you can define different addresses for e-mail recipients who receive different kinds of notifications. This is explained in the next few sections.




Fig. 40: E-mail settings

## 9.7.2 Automatic notifications for readings

Automatic reading notifications can be configured in various ways. For example, you can select an e-mail recipient for the readings, define a schedule for how often the app sends readings, etc.

Note: If the JURA Coffee Professional App is unable to connect to the machine after several attempts, the defined recipient will receive an e-mail with an error message.




Fig. 41: Automatic notifications for readings

# Activate or deactivate automatic notification

Define whether the notifications are sent automatically as soon as the readings for a connected machine have been taken.




Fig. 42: Automatic notification

## **Specify e-mail address**

Specify an e-mail address to which you want to send readings for the connected machine.

## **E-mail frequency**

Under “E-mail frequency” you can define how often the app sends readings to the saved e-mail address. You have three options:

- Manually
  - The e-mail containing readings is sent after each manual update.
- Weekly
  - You can specify that the e-mail containing the readings is sent weekly. You need to state the day or days on which the e-mail is sent and the time at which this happens.
- Monthly
  - The readings are sent once a month. With this option, you need to state the day and time.

## **E-mail format**

Here you can choose between HTML and plain text.

## **CC sender**

Specify whether a copy of the e-mail containing the readings should be sent to the sender too.

## **Automatically reset day counter**

Define whether the day counter on the machine (if present) is reset automatically once you have sent the e-mail containing the readings.

### 9.7.3 Automatic notifications for messages

The app allows you to automatically send the machine’s display messages to a specified e-mail address.

You can define up to two groups which use different types of messages. For example, one group for urgent messages such as “Empty drip tray” or “Fill bean container” and another group for more time-consuming tasks such as “Clean the machine” or “Descalc the machine”.




Fig. 43: Automatic notifications for messages

## Automatic notifications for group 1 messages

Undertake the various settings for the messages for group 1.

### Enable automatic notifications

The “Enable automatic notifications” function allows you to automatically send e-mails containing pre-defined messages to the saved e-mail address.




Fig. 44: Enable automatic notifications

## 9.7.4 Configuration wizard

JURA Coffee Professional includes a configuration wizard which launches automatically the first time the app is used. In a few simple steps, the configuration wizard guides you through how to set up the various JURA Coffee Professional functions.

You can call up the configuration wizard at any time. To do so, go to the general settings.

### Welcome to the configuration wizard

Please take a few moments to configure the app with the wizard.




Fig. 45: Start screen for configuration wizard



# Inserting Smart Connect

The Smart Connect must be inserted into the coffee machine's service socket. This is usually on the top or back of the machine, beneath a removable cover. If you don't know where the service socket of your coffee machine is, ask your dealer or visit [www.jura.com](http://www.jura.com).




Fig. 46: Inserting Smart Connect

## Connecting to the machine

Once the Smart Connect is inserted, it automatically searches for all machines within range (approx. 3 m).

Tap on the machine you want to connect to.

### **PIN function (optional):**


The PIN function on the Smart Connect is deactivated by default.

If the PIN function in Smart Connect has been activated, at this point you will be prompted to enter the PIN.

If the correct PIN was entered when the connection to the machine was established, this is stored in the app and does not have to be entered again to re-connect. If the PIN is changed later on, it must be entered again in order to connect.

The PIN function can be changed in the machine settings.

Once the connection is established, continue with step four.



**Fig. 47:** Connecting to the machine

# E-mail configuration

An e-mail account must be set up in order to send readings and messages via e-mail. Enter the e-mail address to be used to send e-mails.




Fig. 48: E-mail configuration

## E-mail configuration test

A test is now undertaken to check that the e-mail configuration is working properly. Tap on "SEND E-MAIL" to start the test. An e-mail is sent to the address entered.

The test must be successful in order to move on to the next step.




Fig. 49: E-mail configuration test

## Send readings

Automatic reading notifications can be configured in various ways. For example, you can select an e-mail recipient for the readings, define a schedule for how often the app sends readings, etc.




Fig. 50: Sending readings

## Test readings

The app performs another test to check that the readings are being read correctly, the displays are correct and that e-mails are being sent correctly. Tap on “START TEST”. An e-mail is sent to the address entered.

As soon as the test has been completed successfully, the product counter appears on the display.

Once the test is successful, you move on to the next step.




Fig. 51: Testing readings

## Send messages

The app allows you to automatically send the machine’s display messages to specified e-mail addresses.

You can define up to two groups which use different types of messages. For example, one group for urgent messages such as “Empty drip tray” or “Fill bean container” and another group for more time-consuming tasks such as “Clean the machine” or “Descacle the machine”.




Fig. 52: Sending messages

### Group 1 messages

If you specified in step 8 that you wanted to define one or two groups of messages, you can now give the groups different settings.

### Group 2 messages

If you specified in step 8 that you wanted to define one or two groups of messages, you can now give the groups different settings.

## Message configuration test

To test the notification function, you can now generate one of the displayed messages on your linked machine. Shortly after the message has been triggered on the machine, you should receive an e-mail containing this message.




Fig. 53: Message configuration test



# Ending wizard

Tap on "Done" to end the wizard. This ensures that the app works properly.




Fig. 54: Ending wizard

## 9.8 Clear application cache

If this function is confirmed with OK, all machines, readings and default settings are removed from the app / tablet.




Fig. 55: Clear application cache

# 10 Help / instructions

Click on "Help" or "Instructions" to display these instructions for use.




Fig. 56: Instructions


# 11 Notifications

The app sends two kinds of e-mails with the following content:

- **E-mail containing readings:**
  - JURA Coffee Professional logo
  - Type of report sent
  - Model name of machine
  - Machine name and location (if defined)
  - Update time
  - Product counter (plus attached CSV file)
  - Day counter (plus attached CSV file)
  - Maintenance counter (plus attached CSV file)
  - Version (plus attached CSV file)
  - Text line stating how often the e-mail has been sent
- **E-mail containing machine messages:**
  - JURA Coffee Professional logo
  - Type of report sent
  - Model name of machine
  - Machine name and location (if defined)
  - Update time
  - Table containing detailed information about the messages which occurred at the time when you last took the readings and/or a text reporting that there were no messages at this time. Also messages from the machine currently connected (name of message with description and picture).

## 11.1 E-mail containing machine readings:

An example of an e-mail containing the readings of the connected machine.



**Machine readings**

Machine: GIGA X3 Professional  
Location: Defining the current position is switched off  
Update time: 2016-01-15 13:54:03

**Product counter**

Data	Values
Total number of products	4924
Ristretto	288
Espresso	111
Coffee	228
Fiat White	172
Cappuccino	466
Latte macchiato	323
Café latte	66
Macchiato	39
Hot water	2317

Fig. 57: E-mail containing readings

# 11.2 E-mail containing machine message

An example of a message sent by e-mail.



Fig. 58: E-mail containing message

# 12 Support for different languages

JURA Coffee Professional is available in several languages. The app automatically selects the language set on the tablet. If the set language is not available, the app is displayed in English.



Fig. 59: Support for different languages